

PEGACSSA74V1^{Q&As}

Certified Senior System Architect (CSSA) 74V1

Pass Pegasystems PEGACSSA74V1 Exam with 100% Guarantee

Free Download Real Questions & Answers **PDF** and **VCE** file from:

<https://www.leads4pass.com/pegacssa74v1.html>

100% Passing Guarantee
100% Money Back Assurance

Following Questions and Answers are all new published by
Pegasystems Official Exam Center

-  **Instant Download** After Purchase
-  **100% Money Back** Guarantee
-  **365 Days** Free Update
-  **800,000+** Satisfied Customers



QUESTION 1

A subset of users is allowed to attach a scanned document to a case. Which attachment feature do you leverage to implement your solution?

- A. Define a specific access group
- B. Configure an attachment category
- C. Enable attachment level security
- D. Configure an attachment type

Correct Answer: D

QUESTION 2

In which two situations do you use the PegaRULES Log Analyzer to analyze application performance? (Choose two.)

- A. After the application is deployed to a production system
- B. Before migrating an application to a testing system
- C. During User Acceptance Testing
- D. Throughout the application development life cycle

Correct Answer: AD

QUESTION 3

You have a requirement to update account information in an external database using existing stored procedures.

Identify the two steps required to write data to the database. (Choose two.)

- A. Map the external database tables to classes
- B. Configure Obj- methods
- C. Configure SQL connect rules
- D. Map the external database in the application

Correct Answer: CD

QUESTION 4

You want to restrict access to a workbasket to certain users. How do you configure this requirement?

- A. Add the access group for allowed users to the workbasket record
- B. Add a privilege to the workbasket record and to the appropriate access role
- C. Add a skill threshold to the workbasket
- D. Add the access role for allowed users to the workbasket record

Correct Answer: D

QUESTION 5

You are configuring a screen flow as shown below:



Steps three through five must be completed in order. How do you configure the screen flow to meet this requirement?

- A. Select the Enable navigation link and Only allow navigating back to this step options for both steps four and five
- B. Select the Enable navigation link option for both steps, and the Only allow navigating back to this step option for step four
- C. Select the Enable navigation link option for both steps, and the Only allow navigating back to this step option for step five
- D. Select the Enable navigation link option for step four, and the Only allow navigating back to this step option for step five

Correct Answer: D

[PEGACSSA74V1 Practice Test](#)

[PEGACSSA74V1 Study Guide](#)

[PEGACSSA74V1 Exam Questions](#)